

Northeast Michigan Conservation Districts

Alpena, Alcona, Montmorency & Presque Isle

Free Drinking Water Screening Events

(Nitrates & Nitrites)



Drinking Water Well Screening

This service is for private drinking water wells only. Public water supplies are tested regularly. Please do not bring samples from public water supplies or non-drinking water sources. Only drinking water well samples will be tested. You do not have to

	<u>Date</u>	<u>Time</u>	Event Locations
HO.	08/13/14	2 - 4 pm	Alpena Conservation District Office 1900 M-32 West, Alpena, Michigan 49707
6 A	08/15/14	2 - 4 pm	Montmorency Conservation District Office 13210 M-33 North, Atlanta, MI 49709
	08/19/14	12 - 4 pm	Alcona Conservation District @ the Alcona County Fairgrounds 854 Barlow Road, Lincoln, Mi 48742
	09/10/14	2 - 4 pm	Presque Isle Conservation District 658 S Bradley Hwy, Rogers City, MI 49779

Water Well Screening Sampling Procedure

Please follow the directions below to sample your well. Collect samples just before getting them to the sample drop-off. Samples must be less than 48 hours old for a valid nitrate result.

- 1. Fill out the water Sample Information Sheet.
- 2. Pick a tap that supplies water that has not run through any treatment devices (water softener, carbon filter, etc.). An outdoor faucet often works well.
- 3. Run the water for 20-30 minutes before collecting the sample. This will give the pump time to flush the water pressure tank and plumbing so you can collect a valid sample. Disconnect any hoses before collecting the sample; do not sample through a hose. Rinse the sample bottle and lid thoroughly in the water to be sampled; then fill and cap the bottle.
- 4. Label the bottle clearly with your name, the sampling date, and the well name (cottage well, Mom's well, etc.) using a water-proof pen. Put the sample information sheet into a waterproof bag, and then seal the water sample and the information into a second waterproof bag.
- 5. Keep the sample dark and cold (on ice or refrigerated) until it is dropped off.
- All results are confidential. You will be mailed a copy of your results in 8 to 10 weeks, with information about what to do if the concentration of nitrate or nitrite is too high.
- All results are confidential. You will be mailed a copy of your results in 8 to 10 weeks, with information about what to do if the concentration of nitrate or nitrite is too high.

Be sure to fill out the Sample Information Sheet Completely (available at your local Conservation District or downloaded from the Alpena Conservation District your Agriculture Tab) and bring it with your water sample to the drop-off. We need a complete mailing address to get your results back to you. You can get more information from Your Northeast Michigan MAEAP Water Stewardship Technician at 989-356-3596 Ext 108 or http://www.alpenacd.org/your-agriculture.html

How Does Nitrate Get into Water Supplies?

Nitrate is found naturally in soil and water but usually at relatively low concentrations (less than 4 mg/L in water). However, nitrate is highly soluble and is easily transported when contamination sources come into contact with water. Common sources for nitrate contamination include sewage systems, refuse dumps, fertilizers, manure, and decaying plant matter. When water from precipitation or other events is flushed over these sources, the water carries the nitrates with it. As this water percolates into the ground and runs over the surface, the nitrates are carried into groundwater and/or surface water.

What are the Health Risks?

- The major health risk from nitrate/nitrite is to infants under 6 months of age. At this early stage of development, nitrate in the body is transformed to nitrite, which reacts with hemoglobin (the oxygen carrier in the blood) and prevents transport of oxygen. The result is a decreased oxygen supply to the body, often called blue baby syndrome (or methemoglobinemia). It gets this name because the skin often turns a blue or grayish color, especially around the mouth. If these symptoms are noticed, seek medical attention immediately.
- Adults with chronic health problems, such as heart or lung disease or enzyme deficiencies, may be at higher risk from elevated nitrate/nitrite levels.
- Pregnant and nursing mothers should also avoid drinking water high in nitrate/nitrite because of potential effects passed on to the fetus or infant.

There have been a few studies suggesting high nitrate/nitrite may cause certain types of cancer, but this connection is not well understood.

What Steps Can be Taken to Deal with High Nitrate Levels in Well Water?

- Do not boil water to treat for nitrate; this will increase the concentration.
- Bottled or treated water should be used for infants under 6 months of age.
- Other people who should limit consumption of elevated nitrates are those with chronic health conditions such as heart or lung disease, enzyme deficiencies, cancer, or people who are simply uncomfortable about the inconclusive research on long term health effects related to nitrate consumption.
- Steps should be taken to determine and remove the source of the contamination. This could mean reduced fertilizer application, moving of manure piles, cleaning and/or moving of septic systems, and manipulating surface water to flow away from the well head.

There are some treatment options available to remove nitrate from drinking water, including ion exchange, reverse osmosis, and electrodialysis. Prices vary depending on nitrate/nitrite levels and presence of other contaminants in the water. For more information see the World Health Organization (WHO) website: http://www.who.int/water_sanitation_health/dwq/chemicals/rrnitrates/en/and-the-National Science Foundation (NSF) website:

http://www.nsf.org/consumer-resources/health-and-safety-tips/water-quality-treatment-tips

- In some cases drilling a deeper well into a clean aquifer might be worth consideration. In the meantime, bottled water is often the most convenient way to avoid health effects from nitrate contaminated groundwater.
- After receiving results of high nitrate in your well water, retesting the water to confirm the value is recommended before investing in a new well or a treatment system.